

Considerations for Utilizing Frozen Small Grains for Forage

Chris Teutsch, Carrie Knott, and Katie VanValin, University of Kentucky

Once wheat and other small grains adapt to cooler weather in the fall, they are relatively tolerant of cold temperatures and freeze injury. Frost injury in the spring normally occurs when February and March are unusually warm and small grains initiate growth earlier than normal or from an unusually late frost event. Freezing temperatures during sensitive growth stages can significantly impact grain yield. In some cases, the impact on yield can be moderate to severe.

Freeze damage in stands should be assessed after active plant growth has resumed for 5 to 7 days. Active growth in small grains occurs when temperatures are $\geq 40^{\circ}\text{F}$. As much as two weeks may be required during early spring to get 5 to 7 days of temperatures warm enough to promote active growth. Damage may not be detectable prior to this. After 5 to 7 days of warm weather, freeze damage to the tissue will become more evident. Damaged tissue will be water soaked and starting to decay. In some cases, the seedhead may be damaged, but the stem will continue to elongate. In more severe cases, the stem will be damaged and as it decays, the stem will likely lodge and die. In the most severe cases, both the primary and secondary tillers may lodge and die.

Understanding the level of damage will help to determine how to manage the crop. If the level of damage to a small grain stand is severe enough to warrant termination of the grain crop, one option to glean some value from the small grain is to utilize it as forage (Figure 1). Frost-damaged small grains can be mechanically harvested as hay or silage or grazed by cows and/or calves.

Special Considerations

Nitrate toxicity. Nitrates can accumulate to toxic levels in commonly grown forages, including small grains. This most often occurs when heavy nitrogen fertilization is followed by drought or any factor that slows plant growth. As plant growth slows, nitrates are taken up by the plant, but not assimilated into amino acids and protein. After plant growth resumes, nitrates are normally in the safe range in 5 to 7 days. In cattle, nitrate is converted to nitrite in the rumen, and the nitrite is absorbed into the blood stream. Nitrite interferes with the blood's ability to carry oxygen. For additional information on nitrate toxicity including reference ranges for nitrate concentrations, see ID-217: *Forage-Related Disorders in Cattle: Nitrate Poisoning*. Forages that are high in ni-



Figure 1. Frosted small grains can be utilized for both grazing and conserved forage.

trates should not be harvested as hay and green chop or grazed. Nitrates are stable in dry hay and can kill livestock months after harvest. Ensiling forages will decrease nitrate levels 40% to 60%. If high nitrates are suspected, always test the forage before grazing or harvesting.

Key Points

Freezing temperatures at jointing to milk stage significantly reduce small grain yield.

Frost-damaged small grains can be grazed or harvested as hay or silage.

Harvesting for dry hay:

- Evaluate for nitrates.
- Mow early in the day to maximize drying time.
- Mow at boot stage to optimize yield and nutritive value.
- Use mower conditioner to crush stems.
- Maximize swath width of mower-conditioner.
- Rake at 50% moisture.
- Bale at 18% moisture.
- Store under cover.

Harvesting as baleage:

- Evaluate for nitrates.
- Mow at boot stage to optimize yield and nutritive value.
- Use mower conditioner to crush stems.
- Maximize swath width of mower-conditioner.

- Rake and bale at 50% to 60% moisture.
- Make dense bales by driving one gear slower.
- Wrap bales same day as baling.
- Use at least four layers of high quality silage film.
- Inspect bales regularly for holes in the plastic

Grazing small grains:

- Evaluate for nitrates.
- Fill animals up with high quality dry hay prior to introducing small grains to reduce chances of bloat.
- Supply high magnesium mineral supplement to reduce chances of grass tetany.
- Stock small grains at 1 to 2-500 lb calves or 0.5 to 1.0 mature cows per acre.
- Strip or rotationally stock to improve utilization and nutrient distribution.
- Supplement when forage availability is below 1,200 lb/A.
- Remove animals when soils are wet to limit compaction.

Pasture bloat. Pasture or frothy bloat can occur when grazing legume or lush grass pastures, including small grains. It occurs when a stable foam is formed in the rumen. This foam prevents the animal from eructating gases formed during normal rumen function. When hungry animals are given unrestricted access to lush pasture, bloat can occur in less than one hour, but a more common time frame is one to three days. Hungry animals should never be given unrestricted access to small grain pasture. Allow animals to fill up by consuming a high quality dry grass hay in the morning, prior to turning cattle out on a small grain pasture mid-day. Once grazing small grain pasture, animals should have access to a high quality dry hay at all times. Poloxalene, an antifoaming agent, is effective at preventing frothy bloat. It can be mixed with grain supplement, drenched, or fed as a pasture block. However, its effectiveness is dependent upon daily intake. Therefore, mixing it with supplemental feed that is palatable tends to be more effective than supplying it in a pasture block. Some animals are genetically predisposed to bloating, so animals that chronically bloat on high quality pasture should be culled. For more info on bloat see ID-186: *Managing Legume-Induced Bloat in Cattle.*

Grass tetany. Grass tetany or hypomagnesemia is associated with low levels of magnesium in the blood. It most commonly occurs with cows and ewes in early lactation, that are grazing lush perennial pastures, annual ryegrass, and small grains in late winter or early spring. Grasses fertilized with moderate to high levels of nitrogen that are growing on soils that are low in magnesium are most commonly associated with grass tetany. In this case, potassium is taken up instead of magnesium, resulting in very low levels of magnesium in the plant. Pastures with soils low in magnesium should be limed with dolomitic lime and excessive fertilization with potassium and nitrogen should be avoided. Providing a palatable free choice mineral that is high in magnesium (~15%) is the best approach to preventing grass tetany when grazing small grain pastures. For additional info on grass tetany see ID-226: *Forage-Related Cattle Disorders: Hypomagnesemic Tetany or "Grass Tetany."*

Grazing and hay harvest restrictions. Herbicide use in small grains grown for grain could impact how and when small grains can be used for hay and grazing. In addition, rotational intervals for subsequent crops should also be considered. Detailed information on grazing and haying restrictions and rotational restrictions can be found in AGR-6: *Chemical Control of Weeds in Kentucky Grain Crops.* It is important to remember that herbicide labels should always be consulted and followed.

Harvesting for Hay or Silage

Frosted small grain can be harvested as hay or silage. Ideally, the small grain should be allowed to reach the boot-stage (Figure 2). This optimizes the combination of forage quality and yield. In a normal year, wheat should reach the boot-stage around mid-April. If lodging is an issue, small grain could be harvested before the boot-stage. In this case, the estimated yield should be assessed to determine if there is enough biomass to justify mechanical harvest. In general, yields should be greater than 1 ton/A to justify mechanical harvest. To estimate yield, determine the average height of the small grain stand, subtract your

Table 1. Approximate pounds of forage per inch of sward.

| Species | Stand Condition | | | |
|-----------------|-----------------|------|------|-----------|
| | Poor | Fair | Good | Excellent |
| Small Grain | 100 | 150 | 200 | 250 |
| Annual Ryegrass | 100 | 200 | 300 | 400 |

Adapted from "Southern Forages," Third Edition.

mowing height, and multiple the lb DM/A/in of sward (Table 1). For example, if the average height of a small grain stand is 18 inches, the cutting height is 3 inches, and small grain stand is in fair condition,

$$\begin{aligned} \text{Yield in lb/A} &= 18 \text{ in} - 3 \text{ in} \\ &= 15 \text{ in} \times 150 \text{ lb DM/A/in} \\ &= 2,250 \text{ lb DM/A.} \end{aligned}$$

Dry Hay

Small grains can be harvested as dry hay, but curing may be difficult due to poor drying conditions and a heavy crop. The following best management practices will help to enhance field curing.

Evaluate small grains for nitrates. Small grains can accumulate nitrates when plant growth is slowed, especially if moderate or high levels of nitrogen fertilizer have been applied. Nitrates in dry hay do not decrease over time and can kill livestock months later.

Mow early in the day. Mow as soon as the dew is gone. This will maximize drying time.

Use a mower-conditioner. Crushing the stems will allow moisture to escape and shorten curing time.

Adjust mower-conditioner for maximum swath width. Making the mower swath as wide as possible will increase the surface area of forage exposed to the air and radiant energy from the sun.

Ted or rake hay at 50% moisture. This will expose green hay below to air and radiant energy from the sun.

Bale hay at 18% moisture. Baling at 18% moisture will minimize mold growth and heating in the bale.

Store under cover and off the ground. Small grain hay harvest at the boot-stage can be very high in nutritive value. Storing it under cover and off the ground will maintain that quality by reducing storage losses.



Figure 2. In order to optimize yield and forage quality, frosted small grains should be harvested at the late boot to early head stage.

Silage

A better option for conserving small grains is silage or baleage. This option allows small grains to be mowed one day and chopped or baled the next, greatly reducing the chance of rain damage. The following best management practices will help to optimize the ensiling process.

Evaluate small grains for nitrates. Small grains can accumulate nitrates when plant growth is slowed, especially if moderate or high levels of nitrogen fertilizer have been applied. Nitrates in silage or baleage are decreased during fermentation by approximately 40% to 60%. If nitrates are a concern, always evaluate silage before feeding and adjust the ration so that nitrates are in the safe range.

Mow early in the day. Mow as soon as the dew is gone. This will maximize wilting time.

Use a mower-conditioner. Crushing the stems will allow moisture to escape and shorten wilting time.

Adjust mower-conditioner for maximum swath width. Making the mower swath as wide as possible will increase the surface area of forage exposed to the air and radiant energy from the sun.

Haylage

Rake and chop forage at 50% to 70% moisture. Wilted forage can be chopped at 50% to 70% moisture, depending on the silo type (Table 2).

Chop at correct theoretical cut length (TCL). Haylage should be chopped to a TCL of $\frac{3}{4}$ inches to $\frac{1}{2}$ inches. This will aid in silage compaction and exclusion of oxygen.

Fill silo rapidly and compress. Filling silos rapidly limits exposure to oxygen. Compressing silage in bunker silos or bags help to exclude oxygen and enhance fermentation.

Seal silos carefully. Care should be taken to properly seal silos once filled. This excludes oxygen and enhances fermentation.

Do not open silos for at least two weeks. Fermentation takes approximately 14 days until a stable pH is reached.

Consider using an inoculant. Under less than ideal ensiling conditions, inoculating silage with a homofermentative lactic acid bacteria can increase the rate of pH decline and result in a lower final stable pH. Inoculants are best applied at chopping or baling in a liquid form.

Baleage

Rake and bale/chop forage at 50% to 60% moisture. Wilted forage should be baled at 50% to 60% moisture.

Make dense and uniform bales. Slowing ground speed during baling will result in a denser bale. High density bales exclude oxygen and promote fermentation. Uniform bales allow for uniform wrapping and less air space between bales when using a tube wrapper.

Consider using an inoculant.

Under less than ideal ensiling conditions, inoculating silage with a homofermentative lactic acid bacteria can increase the rate of pH decline and decrease final stable pH. Inoculants are best applied at chopping or baling in a liquid form.

Use either plastic twine or net-wrap when baling.

Do not use treated sisal twine when making baleage. The chemicals that the twine is treated with interact with the ultraviolet inhibitor in the plastic film causing it to breakdown prematurely.

Wrap bales the same day as baling. Never bale more hay than can be wrapped that day. Allowing bales to sit overnight will result in squatting, making them more difficult to wrap.

Wrap bales at final storage location. If possible, always wrap bales where they will be stored. Handling and moving wrapped bales often result in damage to the plastic film, allowing aerobic deterioration to occur.

Use high quality plastic film designed for bale wrapping. Plastic film used for baleage contains ultraviolet inhibitors that keep the plastic from being broken down by sunlight. Since the entire ensiling process is dependent on excluding oxygen from the bale, do not compromise on film quality.

Apply at least four layers of plastic. Four layers of plastic film is the absolute minimum that should be applied. Six layers is preferred and if the bales will be maintained for a longer period, use eight layers.

Inspect bales at least weekly and patch any holes immediately. Once air is introduced into a wrapped bale; aerobic deterioration starts almost immediately. It is very important to check bales for holes or tears regularly and to patch those holes immediately with special tape designed for silage wrap. Unlike duct or packaging tape, this tape that contains an ultraviolet inhibitor.

Feed baleage by the next growing season. While round bale silage can produce a quality feed for both beef and dairy cattle, it is not the ideal ensiling package due to its high surface area to volume ration. In addition, the plastic film does not completely exclude oxygen. Over time, oxygen diffuses through the plastic film, albeit very slowly.

Table 2. Optimum moisture ranges for ensiling small grains in various silo types.

| Silo Type | Moisture Range |
|------------------------|----------------|
| Conventional Upright | 63%-68% |
| Upright-Oxygen Limited | 55%-60% |
| Horizontal | 60%-70% |
| Bag | 60%-70% |
| Pile or Stack | 60%-70% |
| Baleage | 50%-60% |

Adapted from "From Harvest to Feed: Understanding Silage Management," UD016, Penn State Extension.

Graze Out Small Grain

Frosted small grain can be grazed, especially if fields are fenced and a water source is available. Grazing is generally the least expensive way to harvest forage. Light weight calves grazing small grains would be expected to gain approximately 1.5 to 2.0 lb per day. In addition, small grains that may be marginal for having enough biomass to justify mechanical harvest, could be grazed. The following best management practices will help to efficiently and safely graze small grains.

Evaluate small grains for nitrates. Small grains can accumulate nitrates when plant growth is slowed, especially if moderate or high levels of nitrogen fertilizer have been applied. Do not graze small grains high in nitrates. Allow plant growth to resume and recheck nitrate levels in five to seven days.

Fill animals up with a high quality dry hay before grazing small grains. Never allow hungry animals unrestricted access to small grain pasture. The abrupt introduction of large quantities of a very high quality forage can cause bloat.

Allow animals access to a high quality dry hay at all times. Access to dry hay will help to prevent nutritional disorders.

Supply high magnesium mineral mix. Grazing small grain pastures can result in grass tetany or low blood magnesium (hypomagnesemia). This is best prevented by allowing cattle free access to a high quality mineral mix that contains approximately 15% magnesium. More information on the University of Kentucky Beef IRM Mineral recommendations can be found at this link.

Stock small grains at appropriate density. The amount of available forage per acre can vary greatly and should be considered when setting a stocking density. Spring stocking densities normally range from 1 to 2-500 lb calves per acre or 0.5 to 1 mature cows per acre. Higher stocking densities are sometimes desired if forage is to be grazed out in a relatively short period of time.

Subdivide or strip graze small-grain pastures. Increasing the animal density per unit area improves forage utilization and manure distribution. Strip grazing can be accomplished by starting at the water source and allocating a new strip of forage every one to three days.

Supply supplemental forage when forage availability is below 1,200 lb DM/A. When forage availability is low, dry matter intake decreases and animals are unable to meet their nutritional needs, even when forage quality is high.

Avoid grazing small grains during wet periods. When soil moisture is high, grazing animals can cause pugging and surface compaction. Simply removing livestock from small grain pastures during wet periods will minimize soil damage.

References

- A Comprehensive Guide to Wheat Management in Kentucky. 2009. UK Ag Extension, IDA-125, Lexington.
- Ball, D.M., C.S. Hoveland, and G.D. Lacefield. 2002. Southern Forages, Third Edition. Potash and Phosphate Institute, Norcross, GA.
- Cheeke, P.R. 1998. Natural Toxicants in Feeds, Forages, and Poisonous Plants, Second Edition. Interstate Publishers, Danville, IL.
- Ditsch, D.C., and M.J. Bitzer. 1995. Managing Small Grains for Livestock Forage. Publication AGR-160, Kentucky Cooperative Extension Service, Lexington.
- Duncan, S., D. Fjell, and G. Kuhl. Grazing Wheat Pasture. Forage Facts Publication of the Kansas Forage Task Force, Kansas State University Agricultural Experiment Station and Cooperative Extension.
- Mayland, H.F. and P.R. Cheeke. 1995. Forage-Induced Animal Disorders. P. 121-36. In R.F. Barnes, D.A. Miller, and C.J. Nelson (eds.) Forages, Volume II: The Science of Grassland Agriculture, Fifth Edition. Iowa State Press, Ames.
- Pitt, R.E. 1990. Silage and Hay Preservation. NRAES-5, Ithaca, NY.
- Shinners, K. 2010. Baleage-The Dry Hay Alternative. Forage Focus-Equipment-December 2010. University of Wisconsin, Madison.